



## Wingate settings for the Galileo Desktop

There is a setting in the wingate software that will cause FPNNet downline machines to be unable to access the host while in Focalpoint after a period inactivity. All workstations lock up at the same time.

It has been found that the Wingate settings can cause the downline terminals to go to sleep.

In Wingate, select SERVICES from the left hand side and locate the service GALILEO on Port 2749 accessing VPNIPC.GALILEO.COM

Double click on the service and move to the SESSIONS tab.

User Services	Port
FTP Proxy server	21
Telnet Proxy server	23
SMTP Proxy server	25
WWW Proxy server	80
POP3 Proxy server	110
SOCKS Proxy server	1080
RealAudio Proxy server	1090
<b>Galileo</b>	<b>2749</b>
Focalpoint	5067
VDOLive Proxy server	7000
XDMA Proxy service	8000
Logfile Server	8010



Ensure this timeout option is not selected.